## **Connecting MyRacePass to Race Manager**

Log into your MyRacePass account



Click the bars in the right.

*	Event De	tais X 🗰 4/23/22: Race Setup X 🖛			.□×				
$\leftarrow \rightarrow$	C	https://12277.admin.myracepass.com/Scoring/Setup/420579	Ę		▣ • =				
🗋 Home	🌣 Most	Visited 🕀 Getting Started 🗋 Coding 🗋 Drone 🗋 Firearms 🗋 IoT 🗋 RFID < Morini CM 200EI - Ben 🗋 Sh	hipping - Logistics 🗋 UV Light (	🗅 Virtulocity 🛛 🚿	Other Bookmarks				
MRP	Mənu	u ▼ 💼 4/23/2022 - Veteran's Motorplex at the Rim ▼							
		Sportsman	5	MRP Live 🕶					
		Pill Options	Transpon	<sup>™</sup> Tools <del>▼</del>					
		O No Pill Draw Lineups will not be determined by pill selections.	No Trans Results wil transponde	No Trans     Reports ▼     Results wil     transponde					
		At Check-In: Auto Draw, After Driver Selection (Fastest check-in process) Pill number is automatically generated for each driver at check-in. Driver cannot press the draw button.	Use Tran	All drivers must provide or rent a transpondor.					
日 (1)	»	O At Check-In: Auto Draw, Before Driver Selection Pill number is automatically generated for the driver at check-in. Driver has the option of pressing the draw button.	O Use Transpo All drivers mus	onders (No Rental st provide a transpond	s) ler.				
		O At Check-In: Manual Entry Pill number is manually entered at check-in using the confirm screen of the driver entry.							
		O After Check-In: Auto Draw Pill number is automatically generated after check-in. Driver has the option of pressing the draw button.							
		O After Check-In: Manual Entry Pill number is manually entered outside of check-in.							
Ľ		Max Pill 100 C Rebase Pill 1							
\$ 0		Save as defaults Rebase Pill does not save a default.		Delete	Class				
https://12277	admin.m	yracepass.com/Scoring/Setup/420579#		Changes Saved	Save				

Then click the MRP Live option. 2 choices will appear. Click on the MRP Live Code selection.

	Event Details	× 🛱 4/23/22: Race Setup ×			¢	> <u>- I X</u>
$\leftarrow \rightarrow$	C	https://12277.admin. <b>myracepass.com</b> /Scoring/Setup/420579			♥ 🗉	∎ ≡
🗋 Home	🌣 Most Visit	ed 🕀 Getting Started 🗋 Coding 🗋 Drone 🗋 Firearms 🗋 IoT 🗋 RFID 🛱 Morini CM 200EI - Ben 🗋 Shippin	ng - Logistics 🗋 UV Ligh	it 🗋 Virtulocity	≫ ⊡ot	ner Bookmarks
MRP	Menu <del>-</del>	i 4/23/2022 - Veteran's Motorplex at the Rim ★				
	S	portsman		🕈 MRP Live 👻		
İ	1	Pill Options	Transpon	MRP Live Code Send Lineups		
	C	) No Pill Draw Lineups will not be determined by pill selections.	No Trans Results wil	🎤 Tools 👻		
	C	At Check-In: Auto Draw, After Driver Selection (Fastest check-in process) Pill number is automatically generated for each driver at check-in. Driver cannot press the draw button.	transponde O Use Tran All drivers	🖶 Reports 👻		
<u>ب</u> 5	» C	At Check-In: Auto Draw, Before Driver Selection Pill number is automatically generated for the driver at check-in. Driver has the option of pressing the draw button.	Use Transponde All drivers r	Settings - sponders (No R must provide a tran	<b>entals)</b> sponder.	
$\oplus$	C	) At Check-In: Manual Entry Pill number is manually entered at check-in using the confirm screen of the driver entry.				
	C	After Check-In: Auto Draw Pill number is automatically generated after check-in. Driver has the option of pressing the draw button.				
	C	) After Check-In: Manual Entry Pill number is manually entered outside of check-in.				
C		Max Pill 100 C Rebase Pill 1				
ф 0		Save as defaults Rebase Pill does not save a default.			Delete Clas	s
Attps://12277.	admin.myrace	epass.com/Scoring/MRPLiveCode/420579		Changes S	aved	Save ~

A window will appear. If you have never downloaded MRP Live click the Download Application button to download MRP Live.



Run the installer and follow the prompts.

🚏 MRP Live Client		a MRP Live Client
Select Installation Folder	æ	Select Installation Folder
The installer will install MRP Live Client to the following folder. To install in this folder, click ''Next''. To install to a different folder, enter it below or click ''B	Browse''.	The installer will install MRP Live Client to the following folder. To install in this folder, click "Next". To install to a different folder, enter it below or click "Bro
Eolder: C:\Program Files (x86)\MyRacePass\MRP Live Client\ Disk C	se	Eolder:  C:\Program Files (x86)\MyRacePass\MRP Live Client\  Browse.  Disk Cos
Install MRP Live Client for yourself, or for anyone who uses this computer:		Install MRP Live Client for yourself, or for anyone who uses this computer:
Everyone		
⊖ Just <u>m</u> e		⊙ Just <u>m</u> e
< <u>B</u> ack	Cancel	< <u>B</u> ack Can

🙀 MRP Live Client			
Installing MRP Live Clier	nt		PASS
MRP Live Client is being installed.			
Please wait			
	< Back	Next >	Cancel

Once the application has been installed click the Launch from Web button to start up MRP Live. After the very first time installing the MRP Live application you will not have to do it again in the future.

*	Event Deta	tails			×	# 4/23/	22: Race S	etup		×	+														¢	•	.o×
$\leftarrow \rightarrow$	С		(	08	http	s://1227	7.admin.	nyrace	epass.co	om/Sco	ring/Set	tup/42	0579							☆	]		$\bigtriangledown$	ᢣ	Ĩ	8	≡
🗋 Home	🌣 Most V	Visited	⊕ Ge	ting Start	ed C	Coding	Dron	•	Firearms	10	T 🗋 R	FID 4	🍄 Morini (	CM 200EI ·	- Ben.	🗅 s	hipping	- Logist	tics (	🗅 UV Ligh	nt (	🗋 Virtu	ulocity	>>	🗋 ot	ner Bool	kmarks
MRP	Mənu	G	et MF	IP Liv€	e Co	ode		Y	Allow thi	<b>is site to</b> d to choo iys allow	o open t se an ap; https://	he mr plication 12277	pl link? 1. ′.admin.n	yracepa	355.00	om to	l						×				≡
			Сор	y and pa	C aste t	onnec	t to MF into yo	RP ur I	oper	n <b>mrpl</b> lin	iks	Choo	ose <u>A</u> ppli	ation		Cancel	av se	/e M and re	RP sults	Live?	o tim	ies to	our race				
×		;	Boofo1f	1-67b8-	4c65	-9a5f-2a	314b17	0c7f Web								ma Ł C	anage Downle	oad A	syste	ation				l			
																			tra	nsponde	<u></u>						
Ŧ		(I	At Che Fastes	ck-In: check-i	Auto n pro	<b>Draw</b> Doess) P	After I	Driver or is au	<b>Selec</b> utomati	ction ically ge								C	) U:	se Tran	nsp.		iettings ·				
<u> ~</u> "		0	IN OIL	annot pr			Dution.																				
77	»	P P	ill num ressing	ber is au the dra	utoma .w bu	atically g	jenerate	d for t	er Sei ne drive	ection er at ch	i ieck-in.							C	) U: All	s <b>e Tran</b> drivers i	n <b>sp</b> o mus	onde st prov	<b>rs (No I</b> ride a tra	Rent nspo	<b>als)</b> nder.		
		0	At Che	o <b>ck-In:</b> ber is m	Man anua	ual Entailly enter	t <b>ry</b> ed at ch	eck-in																			
			After ( ill num utton.	<b>heck-l</b> ber is at	n: A utoma	uto Dra atically g	<b>aw</b> Jenerate																				
		0	After ( ill num	<b>heck-l</b> ber is m	n: M anua	<b>lanual</b> I ally enter	Entry ed outsi																				
ß		M	ax Pill	100			C R	ebase	Pill	1																	
*			Save	as defau	ults	Rebase	Pill does	not sav	/e a def	ault.													1			s	
0																											
2																							Change	əs Sa	vəd	s	ave

	Event De	tails X 🕌 4/23/22: Race Setup X				•	<u> </u>
← -	> C	C A = https://12277.admin.myracepass.com/Scoring/Setup/420579	☆	${igodot}$	⊻ (	ID 🚯	=
🗋 Home	🗘 Most	Visited 🕀 Getting Started 🗋 Coding 🗋 Drone 🗋 Firearms 🗋 IoT 🗋 RFID 倖 Morini CM 200EI - Ben 🗋 Shipp	ping - Logistics 🗋 UV Light	C Virtulocity	»C	] Other Boo	kmarks
MRP	Menu	Get MRP Live Code     Choose an application to open the mrpl link.	_	×			
		Connect to MRP Copy and paste this code into your 3cofo1f1-67b8-4c65-9a5f-2a314b170o7	ave MRP Live? send results and lap ti gement system. nload Application	mes to our race			
3 E 前	»	At Check-In: Auto Draw, After Driver Selection (Fastest check-in process) Pill number is automatically generated for each driver at check-in. Driver cannot press the draw button. At Check-In: Auto Draw, Before Driver Selection Pill number is automatically generated for the driver at check-in. Driver has the option of	Use Transponders	Settings - ust provide or ren ponders (No R	t a entals)	)	1
		Pressing the draw button.     At Check-In: Manual Entry     Pill number is manually entered at check-in using the confirm screen of the driver entry.					
		O After Check-In: Auto Draw Pill number is automatically generated after check-in. Driver has the option of pressing the draw button.					
illest		O After Check-In: Manual Entry Pill number is manually entered outside of check-in.					
Ľ		Max Pill 100 C Rebase Pill 1 C					
¢ Ø		Save as defaults Rebase Pill does not save a default.				Class	
4				Changes	s Saved	s	ave

When the MRP Live application is run for the first time you will see the screen below. Select Westhold Race Manager as the timing software.

Set the Assignments Path to C:\RaceManager\Assign\ by clicking the Browse button and locating the Race Manager Assign folder. If Race Manager is a fresh installation you will have to create the Assign folder. See further down for instructions on creating the Assign folder.

PAS	豊く	First Ti	ime Setup
elect your ti	ning soft	ware	
O MyLaps	Orbits · ©	Westhold	Race Manager
Race Manager Line	ıp Settings —		
Create a file cor	taining all comp	petitors	
Create a lineup	ile per race		
Vill you be us	ing MyRa © Yes	acePass ; · O <sub>No</sub>	to create lineup
– Assignments Path -			
C:\RaceManag	er\Assign\		Browse
			oC

Click Confirm when done.

Creating Assign folder with Race Manager if Race Manager has never been installed.

Go to Race Manager's Assign page. Then click the Add New button.

Race Manager						_ 🗆 🗡
<u>File Options Export Help</u>						
Add New Delete						
		On Track Assign				
Number of Japs:	rack Length: B	reakout (Seconds)	Bac	e Duration (Minute	e):	
			1100	e Baradon (minace	•)•	
Index Trns D Racer No.	Last Name	First Name	Misc	Backup Trns ID	Qualify Time	
Print Lipe up Use Qualify						
Set p Assign Timing						

A window will pop up after clicking Add New. Type in something under New Assignment and click OK. This process generates the Assign folder that MRP Live will use.

New Assignment	×
New Assignment	OK
IEMP	Cancel

Race Manager		
<u>File Options Export H</u> elp		
ITEMP		
Add New Delete	On Track Assign - TE	EMP
Number of Laps: 0 Track Length:	0.000 Breakout (Seconds) 0.0	Race Duration (Minutes): 0
Index Trns ID Racer No.	Last Name First Name	Misc Backup Trns ID Qualify Time
1		
Print Line-up Use Qualify		
Setup Assign Timing		

Once the assignment has been created you can select and delete it.

After clicking the Confirm button in MRP Live. If Enable Network under Race Manager's RMonitor section is not checked you will get an error message. This can also occur if the IP address and port number used are incorrect. See further down about IP address and port number settings.



By default MRPLive will attempt to use the computer's IP address. You will see that in the Race Data section. In this case it is 192.168.1.246. However, be aware that many computers have more than one network interface (wired and wireless). MRPLive pulls up the first one it finds.

This means there can be more than one IP address. This can cause connection issues between MRPLive and Race Manager if MRPLive attempts to connect through the wrong address/network interface.

## We suggest you change the IP address to 127.0.0.1

127.0.0.1 is a special purpose address and is called the localhost or loopback address. All computers use this address. This allows MRPLive app to bypass the network interface hardware so there is no guessing which IP address is the correct one to use.

By default the port number is 50000. This number must match what is in Race Manager's RMonitor section.

IP Address Port number	
Setup     Uploads     ?	X     A     A     P       Setup     Uploads     Help
	Advanced Contraction of the ULTIMATE RACING RESOLINCE
Race Data	Race Data
192.168.1.246 50000	127.0.0.1 50000
<sup>O</sup> Orbits · <sup>®</sup> Race Manager ·	⑦ Orbits · <sup>®</sup> Race Manager ·
MRP Live Code	MRP Live Code
3ccfc1f1-67b8-4c65-9a5f-2a314b170c7f	3ccfc1f1-67b8-4c65-9a5f-2a314b170c7f
□ Offline Mode	⑦ □ Offline Mode
Assignments Path	Assignments Path
C:\RaceManager\Assign\ Browse	C:\RaceManager\Assign\ Browse
□Ignore	⑦ □ Ignore
► · Connect	►-Connect



Click the Connect button and if successful the app will update to show "Connected".



Click the Get Lineups button to get lineups sent over to Race Manager at any time.

